

Anteys 1.4.0
Automated Numerical Time-Series
Evaluation of Varying Sequences Software
User Manual

Copyright © 2011-2018
Frederick W. Vollmer

Contents

	License	ii
	Installation	ii
1.	Introduction	1
2.	Example Usage	2
3.	Data Entry	6
3.1	Data Files	6
3.2	Tree-Ring Files	7
3.3	Manual Data Entry	7
3.4	Automated Data Entry	9
3.4.1	Serial Port Connection	9
3.4.2	Data Coordinate Entry	11
4.	Time-Series Analysis	15
4.1	Detrend	15
4.1.1	Mean	15
4.1.2	Linear	15
4.1.3	Quadratic	16
4.1.4	Cubic	16
4.1.5	Exponential	16
4.1.6	Automatic	16
4.1.7	Spline	16
4.1.8	Fourier	16
4.1.9	Method	17
4.1.9.1	Fit	17
4.1.9.2	Residual	17
4.1.9.3	Standardized	17
4.1.9.4	Ratio	17
4.1.9.5	Ratio log	17
4.2	Filter	18
4.2.1	Delta bar	18
4.2.2	Cubic derivative	18
4.2.3	Ratio	18
4.2.4	Natural	18

4.2.5	Relative	18
4.2.6	Log five year	18
4.3	Mean Master	19
4.4	Data Plot	19
4.5	Cross-Correlation	20
4.6	Bin Tests	20
4.6.1	Bin Correlation	20
4.6.2	Sliding Correlation	21
5.	Data Windowing	22
6.	Segments and Missing Data	23
6.1	Missing Values	23
6.2	Segmented Series	24
7.	Acknowledgements	27
8.	References	28
9.	History	30

License

ANTEVS is Copyright © 2011-2018 Frederick W. Vollmer. This program is distributed in the hope that it will be useful, but without any warranty; without even the implied warranty of merchantability or fitness for a particular purpose.

ANTEVS is free software, however you may not redistribute or post it online without the author's permission. It may only be distributed as the released compressed file package with this file and other included files. Any significant usage, such as a resulting presentation or publication, should include the following two attributions to the program and author:

Rayburn, J. A., and Vollmer, F. W., 2013. ANTEVS: A quantitative varve sequence cross-correlation technique with examples from the northeastern United States. *GFF: Journal of the Geological Society of Sweden*, v. 135, p 282-292.

Vollmer, F. W., 2018. ANTEVS 1.4.0: Automated Numerical Time-series Evaluation of Varying Sequences software. Retrieved from: www.frederickvollmer.com/antevs.

Any reference to the content of the User Manual (this document) may be cited as follows:

Vollmer, F. W., 2018. ANTEVS 1.4.0: Automated Numerical Time-series Evaluation of Varying Sequences software user manual. Retrieved from: www.frederickvollmer.com/antevs.

Installation

On Macintosh OS X, double click the disk image file (.dmg), and drag the Antevs application to your Applications folder, or other desired location.

On Windows, unzip the zip file (.zip) using the Extract All option, and drag the Antevs application to any desired location.

On Linux unpack the gzip file (.tgz), and copy the Antevs application to any desired location.

The Example Data folder contains example files which are referred to in subsequent chapters.

1. Introduction

Time-series arise in situations where a value is measured through time, generally at discrete intervals. Annual intervals commonly occur in natural systems due to seasonal variations in temperature, as displayed in proglacial varves, tree-rings, and glacial ice. Antevs (Automated Numerical Time-series Evaluation of Varying Sequences) is designed primarily to work with such natural time-series, but can be applied to other discrete time-series as well. Antevs is designed to aid in *correlation* of time-series, where an undated times-series, the *unknown*, is compared to a previously dated series, a *chronology*, to determine if they overlap in time and to date the unknown series.

Antevs was developed for the correlation of proglacial varve sequences (Rayburn and Vollmer, 2013), however it includes standard techniques for matching tree-ring sequences, and can convert files between varve and tree-ring formats. It includes routines for reading the Velmex UniSlide digital readout used for tree-ring measurements. A common problem with natural time-series is that of missing data, often due to broken cores. Antevs includes interactive procedures to correlate sequences, such as broken cores, that contain missing values.

Antevs is designed to be user friendly and easy to use, with powerful analytical tools under the hood. It undergoes extensive testing by faculty and undergraduates working on research projects in John Rayburn's varve and tree-ring laboratory at the State University of New York at New Paltz.

Antevs is developed on Macintosh OS X and is compiled for Macintosh OS X, Windows, and Linux. Currently testing is done on OS X 10.11, Windows 7, and Linux Ubuntu. User input is appreciated to improve operation on various platforms.

2. Example Usage


To test the correlation of glacial varve series from the Hudson Valley at Newburgh, NY with the Connecticut Valley at Hartford, CT, download the following North American Varve Chronology (NAVC) Normal Curves files from the North American Glacial Varve Project website (data from Antevs, 1922; Ridge et al., 2012; Ridge, 2012):

HUD29-32AM.txt
CON28-32AM.txt

or open the included TSV (Tab-Separated Value) files:

HUD29-32AM.tsv
CON28-32AM.tsv

Assume one is known and the other is unknown, so open HUD29-32AM as an unknown and CON28-32AM as a chronology (Figure 1). Select them both, and use the command Analyze > Data Plot to view the raw data (Figure 2). Note that the differences in scaling and long wavelength trends makes any correlation difficult to see.



Chronology: CON28-32AM				
	Series	Count	First	Last
1	HUD29-32AM	272	2900	3171
2				
3				
4				
5				
6				
7				
8				
9				

	Series	Count	First	Last
1	CON28-32AM	255	2868	3122
2				
3				
4				
5				
6				
7				
8				
9				

Chronologies 1 of 1 selected

Figure 1. Antevs Data Sets window with an unknown and a chronology file open and selected.




Figure 2. Data Graph window showing the two raw varve example data sets. The difference in scaling and the long term variations make the correlation difficult to see.

To detrend and rescale the data select Analyze > Detrend to open the Preferences Dialog, and set Detrend on, with a 16 term Fourier curve fit, using the Standardized normalization method (Figure 3). In the View Pane check Detrended data for both Unknown and Chronology (Figure 3), and press OK.




Figure 3. Preferences > Detrend pane with Detrend on, and default Fourier and Standardized settings.

The data plot will update to show the data detrended by removing long wavelength trends using a 16 term Fourier curve, and normalizing using standard deviations of the residuals, making the correlation more clear (Figure 4).




Figure 4. Data graphs of raw and detrended data using a 16 term Fourier series.

To perform a cross-correlation and view the resulting correlogram, select Analyze > Correlogram (Figure 5). Use the mouse to examine the r correlation values. Note the strong spike at offset 0 and $r = 0.643$, the best correlation. This demonstrates that the data is correctly correlated, with zero offset between the two series.




Figure 5. Correlogram for two varve sequences showing a strong correlation spike at the best matching year with $r = 0.643$, $z = 6.516$.

Finally, select Analyze > Bin Test to see how subsets of the unknown match the known chronology. The default bin size is 50, with a minimum overlap of 50. Most of the subsets match with zero offset suggesting a robust match.

Tests on NAVC varve data sets known to be correlated suggest that a correlogram with a single correlation spike with $r \geq 0.6$ and $z \geq 6$ is a good potential correlation for varves (Rayburn and Vollmer, 2013). However, definitive correlation acceptance criteria are difficult to quantify, rather, Antevs provides statistical and graphical tools for the evaluation of sequences, recognizing that the ultimate decision for correlation, whether tree-rings, varves, or other time series, lies with the researcher (Grissino-Mayer, 2001; Rayburn and Vollmer, 2013).




Figure 6. Bin correlogram for varve data suggesting a robust fit at 0 year offset.

3. Data Entry

Antevs can read numerous data file formats, including most common spreadsheet files (e.g., Excel, LibreOffice) as described in Section 3.1. A *header row* in these files is used to describe the following data. Additionally, data can be entered directly using the Data Edit Window. A third option is to use automated data collection with the Velmex Unislide digital readout system, commonly used for tree-ring measurements.

3.1 Data Files

Numerous data file formats are supported, the simplest are spreadsheet (e.g., Excel, LibreOffice) compatible lists with a header. The default is a simple tab-separated value (TSV), or tab delimited, format for data, consisting of optional comment lines, a header identifying the data columns, and rows of data. For example:

```
// Hudson Valley; Newburgh; NY
// This is a comment
//
Year<tab>Raw<tab>Comment
2900<tab>44.300<tab>
2901<tab>25.500<tab>approximate value only
```

Headers can include: ID, Year, Raw, Fit, Detrend, Count, and Mean. Count and Mean are special output headers used when creating a mean chronology. Summer, Winter, Comment (or Note) headers are also read and written, but are not otherwise used. It is best to avoid commas in comment lines. The TSV file format is recommended over the space-delimited TXT format, as it can be read and written by most spreadsheet programs, and the comment and header lines provide self-documentation of the content.

A comma-separated value (CSV) format is identical to the TSV format, but uses commas as data delimiters. Note that commas in data fields can potentially cause problems. This format can be also read and written by most spreadsheet programs, for example:

```
// Hudson Valley; Newburgh; NY
// This is a comment
//
Year,Raw,Comment
2900,44.300,
2901,25.500,approximate value only
```

A space-delimited format (TXT), which is for a single sample and has year or sequence number (first column), and total thickness as decimal values in centimeters in the second column. If four columns are detected they are assumed to be year, summer thickness, winter thickness, total thickness. A TSV format is recommended over this format.

Three additional formats used by spreadsheet programs such as LibreOffice Calc and Microsoft Excel are supported: OpenDocument (ODS), Office Open XML (XLSX), and Excel (XLS) spreadsheet formats. The spreadsheet may have comments at the beginning starting with “//”, and must have a header line as described above.

3.2 Tree-Ring Files

A number of specialized formats have been developed for tree-ring files, some of which were based on Fortran punch card formats. Antevs can read and write a number of these, and convert them into other formats.

A Tucson decadal tree-ring raw measurement format (RWL) contains fixed column records with core id, decade or start year, and thicknesses. Multiple cores per file are supported. Thicknesses are stored as six digit integers in units of 0.01 mm or 0.001 mm. When opening a RWL file the precision is determined by the data stop values stored in the file. The desired output format can be set with the RWL units setting in the Preferences dialog (default is 0.001 mm).

A Tucson tree-ring chronology format (CRN) contains a single composite mean chronology which is detrended and has a mean value of 1. To compare a raw unknown measurement to a CRN chronology, the Ratio method should be used for the unknown, as the Standardized method gives a mean of 0. Note that a CRN chronology, as well as a Mean Master chronology (Section 4.3), are not detrended or filtered as this is done when creating the mean chronology. The Detrend and Apply normalize filters settings are therefore ignored for mean chronologies.

3.3 Manual Data Entry

While it is often convenient enter data into a spreadsheet such as Excel or LibreOffice, entering a new time series directly into Antevs is straightforward. In the main Data Sets window select the Unknowns grid, and then the File > New command. A new time series entitled “untitled” will be created (Figure 7). Change the title as required, and use the Edit Data command (pencil and paper icon) to open the Data Edit window (Figure 8).




Figure 7. The Data Series Window after using the File > New command to create a new series. The series can be renamed as required.

By default the first year is 1900, edit the starting year as required (this can also be changed later), and then begin entering data in the Row column. Each entry advances the year by one and moves the cursor down one row (Figure 9).




Figure 8. The Data Edit Window after creating a new series. The start year is given a default value of 1900, edit this as required.

After data has been entered, the Cancel Edits (red X icon) and Accept Edits (green checkmark icon) commands become available. Use Accept Edits to accept the data, this will update any currently open plots. Cancel Edits will revert the data to the previous state last accepted. The

Revert command (blue curved arrow icon) is not currently available because the initial data series was empty. When editing a data set opened from a file, Revert will revert to the state when the file was opened. When finished, accept the edits, close the Edit Data Window, and save the series from the Data Sets Window using the Save As command.

	Year	Raw	Position	Fit	Detrended	Filtered
1	1880	2.400	0.000	2.400	2.400	2.400
2	1881	4.500	0.000	4.500	4.500	4.500
3	1882	3.500	0.000	3.500	3.500	3.500
4	1883					
5						
6						

Disconnected Select "Connect", or enter data for year 1883 manually.

Figure 9. Manual entry of data in the Data Edit window, ready to enter data for the year 1883. Grayed entries can not be edited. The Cancel Edits and Accept Edits icons are now enabled.

Antevs can be used for editing existing time series, and has additional commands such as for splitting and joining rows. If the time series start year must be changed, enter the new value in row 1, and use the Edit > Renumber command. Missing values (Section 5) are entered by “NaN” (or “nan”), or, by default, any negative number.

3.4 Automated Data Entry

Antevs allows automated data collection using the Velmex Unislide digital readout system, commonly used for tree-ring measurements. This has been tested on Windows and Macintosh systems. To collect data measurements, click on the Unknown Grid list and use the File > New command to create a new file (Figure 7). Select the file, rename it as desired, and select Edit > Edit Data. In the Data Edit window (Figure 8), select Edit > Connect (blue plug and socket icon) and enter the required serial port parameters.

3.4.1 Serial Port Connection

The Velmex Unislide digital readout system communicates via a serial port (RS-232 DB9), which requires a USB to serial (RS232) converter on most computers. Numerous converters are available, and their setups, specifications, and quality differ. Converters contain different internal components (processor chip, serial driver chip, output power, surge protection, etc.) and must be compatible with your operating system to ensure a stable connection. Consult your computer technical support to aid in selecting a suitable converter.

AnteVS is set for the default parameters that work in our laboratory on Windows (COM3, 9600 baud, 8 data bits, 2 stop bits, no parity, no flow control). If the default settings do not work, check the information that comes with your USB to serial (RS232) converter, and the Windows hardware information (Control Panel > Device Manager > Ports on Windows 7) to determine the correct settings for your system.

On a Macintosh open the Terminal from the Applications Utilities folder, and enter the following command:

```
ls /dev/tty.*
```

This will list available serial ports. For the Macintosh using a Prolific PL2303 chip set serial USB converter the required port is:

```
/dev/tty.usbserial
```

This port works in our laboratory (Figure 10). An open source driver is available for the PL2303 chip set that works on Macintosh, and is included on the Linux Ubuntu distribution. A free downloadable version from Prolific includes an installation manual (find it using a web search on Prolific PL2303).




Figure 10. Serial port dialog showing settings for a Macintosh computer, these may differ on your configuration.

Future versions of AnteVS will attempt to connect with other data collection devices. The author will work with researchers who are attempting to automate their data collection, currently this must be through a serial port connection.

3.4.2 Data Coordinate Entry

After connecting to the recording device in the Data Edit window using the Edit > Connect (blue plug and socket icon) command, the Connect icon indicates a connection has been made, the Record icon (red circle) has changed from gray to red, and the status has changed from Disconnected to Connected (Figure 11). Antevs has four modes during automated data entry: Disconnected, Connected, Initializing, and Recording. These are indicated in the status bar, as well as by the color of the Record icon (gray, red, yellow, and green respectively). Each mode change is indicated by an audio cue, a click. User instructions are also given in the status bar.




Figure 11. The Data Edit window in Connected mode, after connection with the recording device. The Connect icon (blue plug and socket) indicates connection, the Record icon (red circle) has changed from gray to red, and the status has changed from Disconnected to Connected.

Edit the initial year as required (this can be changed later), and click on the red Record icon to initialize the device. The mode will change from Connected to Initializing, and the Record icon becomes orange (Figure 12).




Figure 12. The Data Edit window in Initializing mode, ready to accept the coordinate of the *start* of the data sequence.

Once in Initializing mode, position the recording device at the *beginning* of the data sequence, in this case at the *start* of the year 1900. The device should be reset to zero at this point, although this is not critical. When ready, use the device to send the coordinates, this will change the mode to Recording (Figure 13).





Figure 13. The Data Edit Window in *Recording* mode, ready to record a data series.

Once in recording mode, advance the recording device to the *end* of the first year, in this case the *end* of 1900, and send the coordinates from the device. The measurement for the first year is now displayed, and Antevs is ready to accept the coordinate for the next year, in this case 1901 (Figure 14).

The Cancel Edits (red X icon) and Accept Edits (green checkmark icon) commands are now available. Use Accept Edits to accept the data, this will update any currently open plots. Cancel Edits will revert the data to the previous state last accepted. The Revert command (blue curved arrow icon) is not currently available because the initial data series was empty. When editing a data set opened from a file, Revert will revert to the state when the file was opened.




	Year	Raw	Position	Fit	Detrended	Filtered
1	1900	3.359	3.359			
2	1901					
3						
4						
5						
6						
7						
8						
9						
10						

Recording Advance the recorder to the end of year 1901 and send the coordinate.

Figure 14. The Data Edit Window in Recording mode after the first measurement, here for the year 1900.

Advance the device to the *end* of the next year, here 1901, and send the coordinates. Continue with subsequent years until data collection is complete. Antevs gives an audio cue, a *beep*, when a decade entry, divisible by 10, is made. Data entry may be paused by selecting Record, and continued by reinitializing the beginning of the *next* year to be entered (the *end* of the last year entered). When finished, use Accept Edits (Figure 15), then Save As in the Data Series Window to save to disk.



	Year	Raw	Position	Fit	Detrended	Filtered
1	1900	3.359	3.359	3.359	3.359	3.35
2	1901	3.280	6.639	3.280	3.280	3.28
3	1902	2.639	9.278	2.639	2.639	2.63
4	1903	3.403	12.681	3.403	3.403	3.40
5	1904	2.652	15.333	2.652	2.652	2.65
6	1905	3.564	18.897	3.564	3.564	3.56
7	1906	3.052	21.949	3.052	3.052	3.05
8	1907	3.186	25.135	3.186	3.186	3.18
9	1908					
10						

Recording Advance the recorder to the end of year 1908 and send the coordinate.

Figure 15. The Data Edit Window after entering a time series, and using the Accept Edits command (green checkmark icon, now gray).

4. Time-Series Analysis

Time-series arise in situations where a value is measured through time, generally at discrete intervals. In natural systems annual intervals commonly occur due to seasonal variations in temperature, as seen in proglacial varves, tree-rings, and glacial ice. Antevs is designed primarily to work with such natural time-series, but can be applied to other discrete time-series as well. Antevs is designed to aid in *correlation* of time-series, where an undated times-series, the *unknown*, is compared to a previously dated series, a *chronology*, to determine if they overlap in time and to date the unknown series.

The analysis in Antevs is broken down into three main parts. *Detrending* is done to remove longer term trends or wavelengths, and to rescale the time-series so they can be more easily compared. A curve is fit to the time-series, and the fitted curve is removed from the data values. *Filtering* may optionally be done following detrending, and can potentially enhance correlations by using neighboring values to smooth local values. Finally, the two time-series are *cross-correlated* to determine if a match can be found between them.

Data plots can be used to visually compare the raw or detrended series, and a *correlogram* allows visual evaluation of the cross-correlation. Additionally, a *bin test* can be done to test the robustness of the match. Finally, a group of correlated series can be used to create a *mean series*, to serve as a master chronology.

4.1 Detrend

Detrending rescales the raw data and removes longer wavelength trends by fitting a curve to the data set, and adjusting the raw data values using the fitted values. This allows sequences with different environmental inputs to be more easily correlated, such as distal and proximal varves, or young and old tree-ring growth. The *residuals* are the data values minus the fitted values:

$$r_i = y_i - \hat{y}_i$$

where \hat{y}_i is the estimate calculated by fitting a curve or function to the data.

4.1.1 Mean

Fits to the mean of y:

$$\hat{y}_i = \Sigma y_i / n$$

4.1.2 Linear

Fits a linear curve:

$$\hat{y} = a + bx$$

by minimizing the squared residuals in y .

4.1.3 Quadratic

Fits a quadratic curve:

$$\hat{y} = a + bx + cx^2$$

by minimizing the squared residuals in y .

4.1.4 Cubic

Fits a cubic curve:

$$\hat{y} = a + bx + cx^2 + dx^3$$

by minimizing the squared residuals in y .

4.1.5 Exponential

Fits an exponential curve:

$$\hat{y} = ae^{bx} + c$$

to the data by minimizing the squared residuals in y using an iterative method. This can be useful for tree-rings that have a regular decrease in width with age, but can fail in many cases.

4.1.6 Automatic

For cubic, quadratic and linear curve fitting a fit is rejected if a negative thickness is predicted, and a lower order curve is tried, until the mean is used. For an exponential fit, the curve is rejected with $b > 0$ or $c < 0$, and a linear curve fit is tried. If a linear fit is rejected with $b > 0$, or a negative thickness is predicted, the data is fits to the mean value of y . Automatic exponential is a common choice for some tree-ring data sets (Cook and Holmes, 1986).

4.1.7 Spline

Fits a cubic spline to the raw data. The Stiffness parameter controls the tightness of the curve (Cook and Peters, 1981).

4.1.8 Fourier

Fits a Fourier series to the raw data. The Low pass frequencies parameter controls the number of components in the series. This is the default method used for varve analysis, with a default setting of 16 (Rayburn and Vollmer, 2013).

4.1.9 Method

The Detrend Method sets the method by which the fit curve is used to detrend the raw data. Common settings are Standardized and Ratio, both of which give unitless values. The Standardized is the default setting, and is recommended unless Ratio is required for compatibility with other files or workers.

4.1.9.1 Fit

Displays the fit curve, \hat{y}_i .

4.1.9.2 Residual

The residual method uses the residuals, subtracting the predicted value, \hat{y}_i , from the data value, y_i :

$$r_i = (y_i - \hat{y}_i)$$

These are not normalized, so units are in centimeters or millimeters, with a mean of zero.

4.1.9.3 Standardized

Standardizes, or normalizes, the residuals by dividing by the standard deviation of residuals. The data is transformed to standard deviations from the fit curve.

$$y' = (y_i - \hat{y}_i) / \sigma$$

Where σ is the standard deviation. This allows comparison of differing series, as it gives unitless numbers with a mean of zero. This is the default method for varve analysis.

4.1.9.4 Ratio

Uses the ratio method:

$$y' = (y_i / \hat{y}_i)$$

The ratio method is commonly used for tree-ring data. It can be biased however, and using residuals (standardized method) is more robust. Values of \hat{y}_i near zero must be discarded to avoid divide by zero errors. The mean of the detrended values will be 1.

4.1.9.5 Ratio log

Uses the Ratio method (Section 4.1.9.4) and applies a log transform for variance stabilization after adding a constant of one-sixth of the series mean to each value.

4.2 Filter

Displays the filters dialog. Filters are applied after detrending the data to normalize the data and potentially emphasize correlations. Normalizing involves smoothing the data by using neighboring values.

4.2.1 Delta bar

Smooths using the average of the nearest neighboring data points, for 3 terms:

$$y'_i = (y_{i-1} + y_i + y_{i+1}) / 3$$

Rayburn and Vollmer (2013) suggest this filter may help emphasize some varve correlations.

4.2.2 Cubic derivative

Orthogonal cubic first derivative filter. Smooths using the cubic derivative of the nearest neighboring data points. This filters the data to look for changes in slope of the series using the first derivative of a local cubic polynomial. The number of terms can be 5, 7, or 9. The 5 term cubic derivative filter can be particularly effective for correlation.

4.2.3 Ratio

Smooths using the ratio of current and previous years:

$$y'_i = (y_i / y_{i-1})$$

4.2.4 Natural

Logarithmic, or natural, change from previous year to current year (Hollstein):

$$y'_i = \text{Log}(y_i / y_{i-1})$$

4.2.5 Relative

Relative change from previous to current year:

$$y'_i = (y_i - y_{i-1}) / y_{i-1}$$

4.2.6 Log five year

Five year natural logarithmic smoothing filter (Baillie and Pilcher, 1973):

$$y'_i = \text{Log}(5 * x_i^2) / (x_{i-2} + x_{i-1} + x_i + x_{i+1} + x_{i+2}))$$

4.3 Mean Master

Calculates a *mean master series* of all open data series, either chronologies or unknowns. Each series is detrended before calculating the mean. Before creating a mean master series, the Detrend option should be checked in the Preferences > Detrend Panel, and either Standardized (recommended) or Ratio methods selected. Detrending rescales the series so each is weighted equally. The data series are not normalized when calculating the mean, so the normalize filter setting does not matter.

Note that detrending using the Standardized method gives values with a mean of zero, and therefore will create negative values. The Treat negative as missing and Display missing as “-9” options (see Section 5) must be off. The Ratio method gives values with a mean of 1, it is less robust, and only recommend if it is required for compatibility, such as when using a Tucson CRN tree-ring mean chronology.

When using either a *mean master chronology*, or a Tucson CRN tree-ring mean chronology to correlate an unknown raw time-series, the mean chronologies are not detrended or filtered as detrended was already done when creating the mean chronology. The Detrend and Apply normalize filters settings are therefore ignored for mean chronologies.

4.4 Data Plot

The Data Plot command plots unknown and chronology thickness, or normalized thicknesses, versus year. It optionally plots best fit curves and raw data for unknowns and chronologies. This plot can be zoomed for a closer view of the data (Chapter 5), and can be used to segment the time-series if there are gaps or missing data (Chapter 6).

As described in previous sections, data plots allow two basic transformations to be applied to assist in correlation. First the data can be *detrended*, to remove trends that may differ between two locations, for example proximal versus distal varves, and then rescaled so the two series are more easily compared. An effective technique is to use a 16 term Fourier function as a low pass filter, with a standardized rescaling using the residuals from that curve (Rayburn and Vollmer, 2013). However, numerous other methods have been proposed for tree-ring data, many of which are implemented in ANTEVS, e.g. exponential, spline, and ratio (Section 4.1).

Secondly, it may be useful to *filter* the original data using a function based on the neighboring data points (Section 4.2). This has similarities to, for example, blur and sharpen filters applied in image software such as Adobe Photoshop and GNU Gimp. The utility of these filters is best determined by trial and error, although the Delta bar filter has been found useful for varves. Other common filters, including those proposed particularly for tree-ring studies, are also provided.

Chapter 6 describes how the unknown data can be *segmented* to assist in reconstructing cores with missing segments. This can be a problem when analyzing tree-ring cores with rotted

sections, or varve cores with destroyed sections. By sliding individual sections of the core relative to one another, it may be possible to reconstruct and correlate the series.

4.5 Cross-Correlation

Cross-correlation is a technique for comparing one time series (an unknown, or undated, series) to another (a dated chronology) at successive time lags, thus allowing the identification of the match with the highest significance (e.g., Davis, 1986). This allows the objective time correlation of two cores, and is the foundation for automated varve and tree-ring correlation techniques. For each of the offsets, ANTEVS calculates a correlation coefficient, r , which varies from -1 to +1, where +1 indicates a perfect correlation. A t value is also reported, which gives an approximate test of the significance of the correlation, the t value also takes into account the number of data points used in the calculation (e.g., Davis, 1986). The offset is reported, which is the offset of the unknown series. The offset for the highest t value, is the most likely correction that should be applied to the unknown years.

As the two series are compared by applying a lag, or offset, the number of overlapping data points goes to zero. As a small number of data points is unlikely to give a significant correlation, a minimum overlap is set to avoid this. The default minimum overlap required for a test is 50, this can be changed in the Preference Dialog > Limits Panel. The Cross-correlation command applies the current filters, first detrending then normalizing, and calculates the cross-correlations and t statistics for each possible match.

4.6 Bin Tests

Two bin or windowing correlation tests can be used to test the robustness of the cross-correlation, and to see if the correlation changes through time. A bin correlation test sequentially groups the unknown data into bins, and runs each bin against the selected chronology. A sliding correlation test uses a window of a set radius that slides along overlapping chronology and unknown segments to look for changes in the correlation through time. The settings for these can be changed in the Preference Dialog > Limits Panel.

4.6.1 Bin Correlation

A bin correlation test sequentially groups the unknown data into bins, similar to bootstrapping, and runs each against the selected chronology displaying the best correlations based on the r and t statistics. This is used to test the robustness of the match and to potentially locate missing varves or tree-rings in an unknown. For example, a marked change in the offset at a given point in the time series may indicate a missing varve or tree-ring at that point. The bin size can be changed in the Preference Dialog > Limits Panel. The bin size must be larger or equal to than the minimum overlap.

4.6.2 Sliding Correlation

A sliding correlation test may be done after an unknown data sequence has been matched with a chronology. A sliding bin, or window, of a set size, given by its half-width, or radius, about an unknown sequence data point, is correlated with the same time window in the chronology sequence for each year. The r and t correlation statistics are calculated from the beginning of the overlapping time sequence plus the window radius, to the end of the overlapping time sequence minus the radius.

This test can show changes in the correlation through time, potentially reflecting local changes in input or environmental conditions between the two sample localities. The test is selected by checking the Sliding checkbox, and setting the value of the Sliding radius in the Preference Dialog > Limits Panel.

5. Data Windowing

The Data Plot can be zoomed in to examine a portion of the time-series allowing more detailed examination. The Zoom Data Window command (green square icon) zooms in on a segment of the time-series, the length of the segment is set in the Preferences > Limits pane using the Data window width setting. Use the Pan Left, Pan Right, Pan First, and Pan Last commands in the View menu to move the window. The step size can be set in the Preferences > Limits pane using the Data window step setting. The Full Data Window command restores the full time-series window.

The Pan Left and Pan Right icons (green arrow icons) also pan the data window, and holding down the Shift key changes these to Pan First and Pan Last. Additionally, the bracket keys (“[“ and “]”) are provided as shortcut keys for Pan Left and Pan Right.

6. Segments and Missing Data

A common problem in natural data sets such as varves and tree-rings is missing data points, as cores or observable varve sequences can be broken or discontinuous. Antevs treats missing data points as NaN (Not a Number) values, which have no numeric value. There can be any number of NaN data points in a sequence. In order to deal with this internally and avoid numerical errors, Antevs uses linear interpolation over the NaN values. This is, for example, the default used by MatLab to deal with NaN values in numerical analysis.


Breaks can be inserted into the unknown time-series, allowing individual *segments* of an unknown time-series to be interactively shifted in time by *incrementing* or *decrementing* them. The segments can be individually compared to the chronology, and slid forward or backwards to match. Additionally, the cross-correlation can be automatically calculated at each step to test the strength of the match.

6.1 Missing Values

Antevs treats missing data points as NaN (Not a Number) values, which have no numeric value, and there can be any number of NaN data points in a sequence. In order to deal with this internally and avoid numerical errors, Antevs uses linear interpolation over the NaN values. This is, for example, the default used by MatLab to deal with NaN values in numerical analysis.

To maintain operability with time series that may contain negative values (such as temperature), Antevs currently has two settings to control how it deals with NaN values. These are set in the Preferences > Options panel. If Treat negative as missing is checked (by default it is not), any negative number is treated as a NaN. The second option, Display missing as “-9”, controls how the NaN is displayed in the Data Edit Window and output files. This is also off by default, however, a common convention in tree-ring data is to use “-9” to signify a missing value. If that is important, turn this option on, and “-9” will be displayed instead of “NaN” in the Data Edit window, and in saved files. Note, however, that treating negative values as NaN will create problems when creating a mean series using standardized detrending. Standardized detrending produces a series with a mean of zero, and will contain negative values.

Figure 16 shows a simple example of a time series with NaN values, and Figure 17 shows the Data Plot of this series. The three NaN values between 1901 and 1905 are interpolated. NaN values can be entered in the Data Edit window, or in input files, as “NaN” (or “nan”), or, if Treat negative as missing is checked, any negative number.



	Year	Raw	Position	Fit
1	1900	1.000	1.000	1.000
2	1901	1.000	2.000	1.000
3	1902	NaN	4.000	2.000
4	1903	NaN	7.000	3.000
5	1904	NaN	11.000	4.000
6	1905	5.000	16.000	5.000
7	1906	5.000	21.000	5.000
8	1907			

Disconnected Select "Connect", or enter data for year 1907 manually

Figure 16. Simple example of a time series with NaN values. The NaN values between 1901 and 1905 are interpolated.




Figure 17. Data Graph of the time series in Figure 17.

6.2 Segmented Series

A common problem in natural time-series is missing data, caused, for example, by broken or incomplete cores. As described in Section 6.1 Missing Values, Antevs allows inserting NaN values to break a series into individual *segments*, however inserting NaN values manually can be

cumbersome. Antevs therefore provides a more interactive *segment editing* mode. The series can be broken up into any number of segments, and the segments can be shifted in time to locate a better match.

To begin segment analysis, open a time-series as an unknown. Segment analysis can only be done on one unknown time-series at a time, this will be the first unknown series selected if multiple unknowns are selected. Next select the Edit > Edit Segments command in the Data Plot window to put Antevs in segment edit mode. All data points will be marked with a white circle. To begin editing, click on the symbol of the data point at the start or end of a segment that you wish to shift. The segment start point will then be marked with a red circle. Shifting the point to the right (to decrease its age) or left (to increase its age) will create a break by inserting a NaN data point, which is marked by a small red circle. Once a segment is created, the segment endpoint will be marked with a yellow circle. The symbols are displayed in the Raw, Detrended, and Filtered curves, any of these can be used for editing. The default symbols can be changed in the Preferences dialog.

To shift a segment, use the Increment Segment and Decrement Segment commands. The Right arrow and Left arrow keys are shortcuts, and holding down the Shift key will increment or decrement by 10. Moving one segment will insert or remove NaN data points and shift the segment. For example, if there are three segments, 1, 2 and, 3 from left to right, shifting segment 2 to the right will add NaNs to its left, and remove them to its right. Once all NaNs to the right are removed, segments 2 is joined to segment 3. Selecting the first or last point in the series will shift the entire series.




Figure 18. Data Plot window with a segmented unknown (red 367101) compared to an identical chronology (blue 367101). The unknown has two segments, the second, starting at 1721, as indicated by the red circle, has a one year offset from its original start position at 1720. A NaN value has been inserted at 1720, as indicated by the small red dot.

Mistakenly reversed segments may occur during data collection, for example during the collection of broken cores. The Reverse Segment command may be used to reverse an individual segment to look for a match.

If open, the Correlogram window will update and show the correlation values. Use the *Accept Edits* command to accept the edited values. The *Cancel Edits* command will revert to the state when *Accept Edits* was last called. The *Revert* command reverts to the state on opening the file.

Note that the ID field is used to give each entry a unique identification number. When shifting segments new data points are added as NaN values, and these will be given the next available highest ID. The ID can be any integer value, such as the initially estimated year sequence, or a series starting with 0 or 1. When reading in a data file, Antevs will assign an ID value if one is missing. This allows the Year field to be modified, as the ID is not modified when renumbering or inserting missing values. When deleting, splitting, or combining rows, or editing segments, the next available unique ID number is assigned. The *Set ID from Year* command in the Data Edit window will set the ID field to the Year if desired.

7. Acknowledgments

ANTEVS was written after several years of prodding by John A. Rayburn. Thanks to John for numerous suggestions and bug reports, his first mission on each release has been to try to make it crash, greatly improving the software's stability over the years. David Barclay has been of great help in explaining some of the finer points of tree-ring correlation techniques, software, file formats, and other details. I thank Jack Ridge for discussions, inspiration, the pleasure of attending his field excursions, and examining his varve cores in person. Roger LeB. Hooke inspired me as a graduate student, and I continue to value discussions with him. Andrew Breckenridge assisted with helpful suggestions and enthusiasm. I have enjoyed field time and discussions on Pleistocene geology with David A Franzi, David J. DeSimone, Stephen Wright, Duane Braun, and many others. As a structural geologist, I am grateful to be able to share in the enthusiasm of the active members of the Friends of the Pleistocene.

I thank student researchers Nicholas J. Gonda, Alaina N. Walag, Megan King, and Jamie Vornlocher for their work using ANTEVS in the laboratory, for suggestions, and bug reports.

8. References

- Antevs, E., 1922. The recession of the last ice sheet in New England. *American Geographical Society Research Series* 11, p. 1-120.
- Baillie, M.G.L., and Pilcher, J.R., 1973. A simple crossdating program for tree-ring research. *Tree-Ring Bulletin*, v. 33, p. 7-14.
- Brewer, P., Murphy, D., Jansma, E., 2011. TRiCYCLE: A universal conversion tool for digital tree-ring data. *Tree-Ring Research* 67, p.135-144.
- Cook, E.R., 1985. A time series analysis approach to tree ring standardization. Ph.D. dissertation, University of Arizona.
- Cook, E.R., and Richard L. Holmes, R.L., 1986. Users manual for program ARSTAN. Laboratory of Tree-Ring Research, University of Arizona, Tucson, USA.
- Cook, E.R. and Peters, K. 1981. The smoothing spline: a new approach to standardizing forest interior tree-ring width series for dendroclimatic studies. *Tree-Ring Bulletin*, v. 47, p. 45-53.
- Cook, E.R. and Peters, K. 1997. Calculating unbiased tree-ring indices for the study of climatic and environmental change. *The Holocene*, v. 7, n. 3, p. 361-370.
- Cybis Wiki contributors, 2015. "Tucson format," Cybis Wiki, , http://www.cybis.se/wiki/index.php?title=Tucson_format&oldid=2472 (accessed February 13, 2016).
- Davis, J. C., 1986. *Statistics and Data Analysis in Geology*, Second Edition. John Wiley & Sons, New York, USA. 646 p.
- Fritts, H.C., Mosimann, J.E., and Bottorff, 1969. A revised computer program for standardizing tree-ring series. *Tree-Ring Bulletin*, v. 29, p. 15-20.
- Grissino-Mayer, H.D., 2001, Evaluation crossdating accuracy: a manual and tutorial for the computer program COFECHA. *Tree-Ring Research*, v. 57, n. 2, p. 205-221.
- Holmes, R.L, 1983. Computer-assisted quality control in tree-ring dating and measurement. *Tree-Ring Bulletin*, v. 43, p. 69-78.
- Melvina, T.M., Briffaa, K.R., Nicolussib, K., Grabner, M., 2007. Time-varying-response smoothing. *Dendrochronologia*, v. 25, p. 65-69.
- Press, W. H., Teukolsky, S. A., Vetterling, W. T., and Flannery, B. P., 2007. *Numerical Recipes: The Art of Scientific Computing*, Third Edition. Cambridge University Press, Cambridge, UK. 1235 p.
- Rayburn, J.A., and Vollmer, F.W., 2013. ANTEVS: A quantitative varve sequence cross-correlation technique with examples from the northeastern United States. *GFF: Journal of the Geological Society of Sweden*, v. 135, p 282-292.
- Ridge, J.C., 2012, The North American Glacial Varve Project: (<http://eos.tufts.edu/varves>), sponsored by The National Science Foundation and The Department of Earth and Ocean Sciences at Tufts University, Medford, Massachusetts.
- Ridge, J.C., Balco, G., Bayless, R.L., Becks, C.C., Carter, L.B., Dean, J.L., Voytek, E.B, and Wei, J.H., 2012. The new North American varve chronology: a precise record of southeastern

Laurentide ice sheet deglaciation and climate, 18.2–12.5 kyr bp, and correlations with Greenland ice core records. *American Journal of Science*, v. 312, p. 685–722.

Vollmer, F.W., 2018. ANTEVS 1.4.0: Automated Numerical Time-series Evaluation of Varying Sequences software. Retrieved from: www.frederickvollmer.com/antevs.

9. History

1.4.0.5 (2018-06-18)

- Added *Sliding correlation* option to *Bin test*.
- *Preferences* dialog updated with listbox control.
- Fixes to text controls, replaced all TStaticText controls with TLabels.
- Updated math and statistics routines to use open source library, e.g., non-linear curve fitting using Levenberg-Marquardt method, and linear equation solutions with LU decomposition from Jean Debord's DMath 0.9.0.
- Rewrote linear, quadratic, and cubic curve fitting routines from scratch to remove external dependencies.
- Removed all TIdleTimers that were used to enable menus and controls. The controls are now updated as necessary in command and message procedures.
- Updated with Lazarus 1.8.4 and Free Pascal 3.0.4.
- Numerous code refactoring changes.

1.3.6.4 (2016-12-03)

- Fixed and improved segment editing. Now segments can be slid forwards and backwards, and individual segments move independently.
- Now displays years in short segments without decimal points
- Fixed delete selected year in series editing window, was deleting the last year instead of selected year.
- Fixed a divide by zero bug that occurred during the display of a series with two data points.
- Fixed *About* box display.

1.3.5.5 (2016-11-21)

- Changed messaging procedures from PostMessage to Dispatch message.
- Fixed metadata editing in spreadsheet file formats.
- Fixed initial year assignment bug.
- Added *Home Page* command.
- Added automatic version checking, and *Check for Updates* command.
- Updated grids.
- Segment editing entirely replaced, see Section 6.2.
- Graph Window renamed Plot Window.

1.3.4.1 (2016-04-27)

- Fixed display of segments when reopening file saved with NaN values.

1.3.3.7 (2016-04-03)

- Now automatically rennumbers when inserting a NaN during graphical editing.
- Saves and reads three lines of metadata in Tucson decadal crn files.

- Now correctly reads Tucson decadal rwl files with negative years.
- New command Edit Metadata to edit metadata.
- After data is entered in the Data Edit window with the Vemlex recording device, the window can now be closed without the Accept Edits warning.
- Edit New now allows more than one “untitled” files.
- In file window mouse Shift-Click selection now selects a block of rows. Command-Click (Control-Click) toggles one row as previously.
- Fixed status display in the Graph window.
- Removed the confusing Break Segment command. Now, in Edit Segments mode clicking inside a segment cuts it (click again to undo), and clicking on the start of a segment selects it. See Section 6.2.

1.3.2.4 (2016-02-22)

- Bound resource files into executable for Windows and Linux.
- Added back Zoom Data toolbar pan buttons, press *Shift* to pan to first or last year.
- Added saving of comments to main master file.
- Added Encapsulated Postscript and DXF vector export.
- Consolidated graphics output to Export Image commands.
- Added Page Size command for Data Graph and Correlograms.
- Work on User Manual, including Chapter 8 to clarify Data Windowing.
- Removed “Unknown” and “Chronology” from Data Graph legend.
- Compiled with LCL 1.6.0 and FPC 3.0.0 optimizations.
- Fixed 999 bug in RWL writing.

1.3.1.14 (2016-02-13)

- Optimized data grid scrolling.
- Optimized messaging.
- Remembers last data file directory.
- Fixed index range bug in splines.
- Data plots now update during editing in Data Window.
- Correlogram now correctly updates when no data list is selected, and when lists are opened or closed.
- The edited state can now be saved by the Accept Edits command either during editing in the data window, or during editing using the Edit Segments command in the plot window. The *Cancel Edits* command restores to that state.
- Removed Refresh toolbar button, Auto-Refresh is on by default.
- Removed Zoom Window pan toolbar buttons from Plot Window, the *Cmd-[(Pan Left)* and *Cmd-] (Pan Right)* and *Shift Cmd-[(Pan First)* and *Shift Cmd-] (Pan Last)* keys are now enabled for this.
- Added automatic renumbering for edit operations. This already occurs for segment editing.
- Added automatic ID assignment for editing. The ID is always a unique number.
- If no IDs are input a sequential value starting at 1 will be assigned.

- Added ability to change plot frame color, default is now black with white background.
- Added additional icon sizes for Windows 7 and up.
- Added *Reverse Segment* command.
- Cleaned up some dialog control display issues.
- Now reads rwl files containing non-standard LFLF sequences output by some software.
- The rwl file units are now correctly set during reading by checking for stop markers “999” (0.01 mm) or “-9999” (0.001 mm) in file (Cybis Wiki contributors, 2015). Note “999” stop marker disallows 9.99 mm rings in 0.01 mm files.
- Changes to 0.001 mm rwl file reading and writing following D. Barclay (per J. Rayburn). Writing uses “-9” instead of “0”. Reading treats any negative value as missing, not “0”. See Cybis Wiki contributors (2015) for “0” convention.
- Changes to reading and writing missing values in 0.01 mm rwl files following Cybis Wiki contributors (2015). Writing uses “-999”. Reading treats any negative value as missing.
- Added reading of rwl meta-data headers.
- Added writing of meta-data headers.

1.3.0.3 (2015-06-29)

- Serial Settings, Initialize Read, Split, and Preferences dialogs re-configured for better cross-platform consistency. Additional tooltip help added. TLabel controls replaced with TStaticText.
- Added “ID” column to provide a unique identifier for each measurement to allow editing of years without losing track of initial input values. See Section 5. Feature request by Andrew Breckenridge.
- Added command to set the ID from the Year. This will change the ID to the current year, and would normally only be done during initial measurements.
- Fixed the reading of spreadsheet files (ods, xls, xlsx) so column order is not important.
- Made “Ratio Log” a separate method option instead of using checkboxes, this uses the Ratio method followed by log normalization (COFECHA option). A combobox allows separate methods for unknowns and chronologies.
- Numerous internal changes to preferences code for easier updates.
- Added visual segment editing for missing data and broken cores with 6 new segment analysis commands, see Section 5.
- New icon.

1.2.1.1 (2015-01-29)

- Made default for treat negative as NaN to false to avoid problems with mean series when using standardized detrending.
- Fixed bug causing crash when renaming Chronology.
- Fixed widths in initial display of columns.
- Currently line count: 159,471.

1.2.0.13 (2015-01-07)

- Added StatusBar to MainWindow and DataWindow.
- Replaced Timers with Messages to communicate between windows.
- Replaced StringGrids with DrawGrids to avoid internal data duplication.
- Numerous internal changes for utilizing Messages and DrawGrids, resulting in more maintainable code for future updates.
- Grayed uneditable cells in grids.
- Fixed LogForm to open in front when Preferences > Options > Display log is checked.
- Added date time string to LogForm, and added left margin.
- Added Unknown and Chronology dates to Correlogram status bar. The correlogram status bar now contains all information contained in the Log file.
- Fixed 'Save As' command to rename file in MainWindow grids.
- Changed 'Clear' to 'Close' in file close warning dialogs.
- Fixed the extra warning dialog when closing a file modified in the DataWindow.
- Modified to 'Revert' command. In the Data Window, Cancel Edits reverts to the last state saved with Accept Edits, while Revert returns to the state when the file was opened.
- Numerous changes to Data Edit Window input procedures. Current mode and user instructions are provided in the status bar (instead of dialog boxes) to clarify. A default year is given (1900), which can be edited. Data may be entered manually or using the recorder. The modes: Disconnected, Connected, Initializing, and Recording are indicated in the status bar, as well as by the Record button (gray, red, yellow, green). Mode changes also have audible cues.
- Fixed Error Opening File dialog to display file name.
- Fixed an error that cleared the file list when opening a new ods, xls, or xlsx file.
- Updated the spreadsheet opening/saving component. Previously a file open in Excel or LibreOffice could not be opened simultaneously in Antevs due to file privileges. It is now possible to do so, however, with the risk of file version collision. Save the file in one program before opening it in the other.
- DataWindow tool hint "Insert Row" changed to "Insert Row Before".
- DataWindow Append button switched position with Insert.
- Changed default bin size from 100 to 50, and minimum overlap from 60 to 50.
- Added mouse-over status to Frequency Graph. This is an experimental graph, and its interpretation is not straight-forward. It is a periodogram, a modulus-squared of the Fourier transform.
- Added "Time" as input alias header for "Year", to accommodate monthly, hourly, etc., time series.
- Missing data is now supported, see Section 5.

1.1.0.3 (2014-10-04)

- Updated to minor version 1.
- Internal modifications to file save routines.
- Changed Edit > Clear command to File > Close, and added Cmd-W accelerator key.
- Changed Auto-Update default to true.

- Grids now save column widths between sessions.
- Moved Analyze > Refresh to View > Refresh, fixed disabled command when Auto-Update is off, changed accelerator key from Cmd-H to Cmd-R.
- Paint pickers updated to use opacity.
- Added ability to open Excel XLS and XLSX files.
- Fix to correctly save initial comment lines in File > Save As.
- Modified data collection routines to ask for initial date.
- Linux: Fixed image centering bug using work around.
- Linux: Fixed Preference dialog so visible pane always matches panel listbox selection.
- Expanded User Manual.

1.0.6.6 (2014-02-23)

- Numerous changes to the Data Edit Window to implement reading the Velmex UniSlide digital readout for logging tree-ring data. See section in ANTEVS User Manual on Data Collection.
- Implemented messaging to replace global flags and minimize recalculations.
- Fixed a bug that was disallowing multiple open series for some formats.
- Added warnings for saving data.
- Disallowed opening series with identical names.
- Fixes to File Save dialog.
- Added Save As command to Data Edit window.
- Changed the name from ANTEVS (Automatic Numerical Time-series Evaluation of Varve Sequences) to ANTEVS (Automated Numerical Time-series Evaluation of Varying Sequences).

1.0.5.9 (2013-04-29)

- Fixed Revert command in data edit window. This command reverts the data to the last time it was opened or saved.
- Added Select All command.
- Removed deprecated Clear All command, use Select All + Clear commands.
- Made Precision apply to displayed data as well as file output.
- Added ODS (OpenDocument), XLS, and XLSX spreadsheet formats to Save As command.
- Added Export Sets command to save all selected data sets in one TSV, CSV, ODS, XLS, XLSX, or RWL (decadal) format file. See Brewer et al., 2011.
- Added ODS spreadsheet format to Open command.
- Open command now detects and opens TSV, CSV, ODS files, in addition to RWL format files, to open multiple sets files created with Export Sets command.

1.0.4.10 (2013-04-22)

- Grouped graph components in SVG output for easier editing.
- Fixed text vertical alignment in SVG output.
- Changed menu item Save As Vector Graphics to Export SVG.

- Removed Unicode => symbol, not recognized by AI Helvetica.
- Added target CPU and system info to About dialog box.
- Added comment editing.
- Added Split command to split, join and renumber data measurements.
- Removed depreciated Combine command.
- Preference file modifications.

1.0.3.7 (2013-04-08)

- Fixed floating point error caused if detrend curve exactly equals data.
- Fixed preference button hints.
- Allow opening of Preference dialog without selecting or opening data.
- Added menu options to open Preference dialog Detrend and Filter pages.
- Added fit curve color selection.
- Added About dialog.
- Compiled with FPC 2.6.2, LCL 1.0.8.

1.0.2.5 (2013-04-01)

- Fixed bug causing freeze when opening Precision dialog.
- Precision now stored in preference file.
- Precision settings moved to Preferences dialog.
- Added ANTEVS header to TXT files.
- Changed default file type to TSV (tab separated values).
- Modified Save As for TXT, TSV, CSV files to save Year and Raw columns only.
- Added z score, standard deviation, count, and offset to cross-correlation graph.
- Changed precision to three places in cross-correlation display.
- Displayed maximum t value now always corresponds to maximum r value.
- Added p to t graph.
- Changed title of 'Filters' dialog box to 'Preferences'.
- Changed page selection in preference dialog to combobox.
- Detrend, Filters, and View preferences are now saved to preference file.
- Added option to turn off display of cross-correlation significance in Preferences Options tab.
- Added stroke selection for graph data.
- Fixed runs trend bug.

1.0.1.4 (2013-03-16)

- Compiled with Free Pascal 2.6.0 and Lazarus 1.0.6.
- Fixed missing tick marks bug.
- Fixed tick marks stroke color.
- Fixed vector font export bug, fonts are now filled instead of stroked.
- Fixed incorrect log references.
- Fixed fill color bug in SVG export.

1.0.0.1 (2012-10-31)

- First official release for review.

0.0.20 (2012-09-18)

- Compiled with Free Pascal 2.6 and Lazarus 1.0.
- Fixed Save As command to save raw data instead of detrended data.
- Added new Save Detrend command saves detrended data.
- Added preliminary frequency spectrum (periodogram) graph, use Window > Frequency to view.

0.0.19 (2012-04-15)

- Added multiple colors to data graph.

0.0.18 (2012-04-08)

- Recompiled on Free Pascal 2.6.0.
- Added Spline detrending, following COFECHA.
- Added Log transform for the Ratio method, following COFECHA.
- Added csv and tsv data files for both raw data and mean masters.
- Combined file formats into Open and Save As dialogs, and removed multiple Open and Save As commands.
- Removed Delta bar past filter.
- Added Link checkbox to link unknown and chronology detrend methods.
- Added max and mean labels to correlogram and bin graphs.
- TODO: Interpolate missing values.
- TODO: Debug RWL and CRN missing value and end data values, 999, -999, -9999, etc.

0.0.17 (2012-02-24)

- Added ability to select and view multiple data sets by control (Windows) or command (Mac) clicking. Note that only the first selected file in the unknown and chronology grids is used for most operations (cross correlation, saving files, etc.).
- Added data windowing with panning to allow detailed view and stepping through data.
- Added cross-correlation of data window.
- Added Count column in data edit grid, this gives data counts for means and CRN files.
- Fixed memory leak.
- Added Save As CRN Chronology for mean and CRN data series.
- Enabled Preferences command on Mac (same as Filters).

0.0.16 (2012-02-05)

- Added Fourier detrending for variable terms.
- Added two delta filters mainly for use with Standardize detrend method. These are more stable and handle zero thicknesses naturally (no division by zero). Note the Cubic derivative

is also stable. Note that the common Ratio method normalize filters do not work well with the Standardize detrend method, because the mean is zero instead of one.

- Added Delta bar filter: $y1' = y1 - (y0+y1+y2)/3$.
- Added Delta bar past filter: $y3' = y3 - (y0+y1+y2)/3$.
- Removed Difference filter, this was identical to Delta bar past with 1 term.
- Removed polynomial smoothing detrending as not effective, was similar to Fourier with many terms.
- Removed quadratic polynomial derivative filter as not effective, overly smoothed data.
- Added mean toolbutton.
- Added detrend Fit method, this gives the fit curve for display or saving to file. It is not useful for correlation.
- Stacked raw, detrend, and filtered data graphs.
- Numerous additional fixes.

0.0.15 (2012-02-19)

- Changed name to ANTEVS (Automated Numerical Time-series Evaluation of Varve Sequences), or Antevs.
- Added automatic option for detrending polynomial curve fitting. See Detrend above.
- Changed automatic exponential to reject linear fits that predict negative thicknesses. This removes some errors in detrending (e.g., calculating a mean for ny005.rwl, series 22).
- Added orthogonal quadratic polynomial smoothing filters. See Normalize above.
- Added orthogonal quadratic and cubic polynomial first derivative filters. See Normalize above.
- No longer saves window size when maximized.
- Added residuals and standard residuals detrend methods. See Detrend above.
- Added data series name edit.
- Made Filters dialog nonmodal.
- Added Detrended column to Data Edit grid.
- Enabled Quit command in Windows.

0.0.14 (2012-02-16)

- Fixed saving of mean files.
- Rewrote handling of zero thicknesses, only used during normalization to avoid division by zero or log zero.
- Stacked graphs with scales on all curves.
- Fixed update of Data Edit grid when a chronology is viewed.
- Fixed update of main data set grid after editing data.
- Optional runs trend calculation is done simultaneously and viewed on a separate stacked graph.
- Runs trend algorithm is modified slightly following Corina; an up/down/same = up/down/same match gets +1, a same = up/down gets +0.5, otherwise no match gets 0.

0.0.13 (2012-02-06)

- Rewrote cross-correlation procedure to minimize potential round off, no change in functionality.
- Fixed bug in graph frame drawing.
- Fixed bug in exponential fitting, was not fully converging.
- Added y scale labels to data graph for raw data on right. Filtered data scale remains on left. Grid is drawn for filtered data unless only raw or detrend fit is on.
- Fixed Clear tool button, was not working.
- Fixed two bugs causing random errors in mean calculation.
- Changed menu text from "Cross-Correlation" to "Correlation", no change in functionality.

0.0.12 (2012-02-05)

- Added Zoom commands and controls, including mouse dragging.
- Fixed Accept Edits command in Data Edit window, was not keeping edits.
- Changed Processed to Filtered for clarity.
- Changed Data View to Data Edit.
- Added toolbar to Data Set window.
- Added data names to graphs.
- Fixed y axis scaling error on data graph.
- Added correlogram caption.
- Linked Filter Normalize controls, so changing unknown now changes chronology. Added an option to turn linking off, but there is no reason for these to differ. May combine in next version.
- Fixed Save As, was not enabled.
- Added more information in status bar.

0.0.11 (2012-01-28)

- Added graphics buffer to fix slow redraw on Windows.
- Fixed focus loss when closing filters dialog on Windows.
- Fixed divide by zero error

0.0.10 (2012-01-28)

- Fixed window position xml preferences
- Fixed error reading rwl, 999 entries now excluded as well as -9999
- Fixed data view, was not updating on data grid focus change
- Enabled view detrend as always available
- Fixed error in mean calculation, was not detrending with correct settings
- Added save view options in preferences
- Fixed divide by zero error

0.0.9 (2012-01-25)

- Internal changes for easier maintenance

- Fixed compatibility with OS X 10.5

0.0.8 (2012-01-18)

- Added graph of offset values to bin test correlogram.
- Added color keys for curves on graphs.
- Restored ability to calculate mean chronology.
- Restored option to view log output.
- Fixed bugs in bin test.
- Made auto-refresh optional.
- Added Refresh command and toolbar buttons.
- Fixed label and grid spacings to auto-size.
- Added ability to open CRN files.
- Added ability to detect and open four column TXT files.
- TXT file is checked for non-sequential values.
- Added Open command that uses file extension to determine file type.
- Added quadratic and cubic detrending options.
- Turned off automatic renumbering when editing a file.
- Added Renumber command.

0.0.7 (2012-01-08)

- Completed graphical display of bin test and data display.
- Simplified analyze options.
- Depreciated log test display window.
- Added curve fitting and detrending algorithms.
- Implemented Marquardt non-linear curve fitting.
- Added best-fit curve display to data graph window.
- Redesignated growth correlations as normalize filters, e.g., Natural and Difference.
- Added additional normalize filters, e.g., Log five year and Two year sum.
- Depreciated cross-association (available in Filters Extra tab).
- Depreciated runs analysis (available in Filters Extra tab as S_{Ign}).
- Experimental implementation of area correction algorithm (depreciated).
- Implemented chronology data display.
- Implemented unknown data editing with preview and restore.
- Added minimum thickness value with default of 0.001.
- Added automatic update of Data View, Data Graph, Bin Test and Correlogram windows.
- Created new icon.
- Added preference file to remember window locations and sizes.
- Added vector graphics SVG output of graphs.
- Added PNG, BMG, and JPG bitmap output of graphs.

0.0.6 (2011-12-11)

- Added Graph Window.

- Added Thickness Graph.
- Added Growth Graph.
- Added year offsets to Log Window analyses to assist in locating matches.

0.0.5 (2011-12-03)

- Added 'Precision' command to set precisions in files to avoid precision loss when converting varve to tree-ring format.
- Enabled Analyze and Window commands from Log Window.
- Added Mean Growth command.
- Added Growth Correlation command.
- Modified Bin Test to allow setting of additional filtering parameters, including multiple matches per bin.
- Added desktop icon.

0.0.4 (2011-11-21)

- Rewrote Trend Percentage algorithm.

0.0.3 (2011-11-20)

- Added Normalize.
- Added Normalized Mean.
- Added Cross-Correlation.
- Added Runs Correlation.
- Added Bin Test.

This page intentionally left blank

